

DO NOT TURN THE POWER OFF DURING THIS PROCESS.

BIOS Installation

Copy the attached file in to the following folder:

AstroJet 1000-5 (v450 r06 p11.fbios)
C:\Program Files\AstroJet\BIOS\450

AstroJet 3600/3800 (v280 r06 p20.fbios)
C:\Program Files\AstroJet\BIOS\280

1. Load the AstroJet software for your printer into your computer.
2. Connect the computer to the printer and turn the printer **ON**.
3. Select the "AstroJet Control Panel" icon on your desktop and double click on it.
4. Select "Properties", then select "Update BIOS".
5. Click on the **Update BIOS** button. When the software completes the update check the printer's control panel for the new BIOS level.